

VISITREND +VISIPLOT

POCKET REFERENCE













A Product of Micro Finance Systems Distributed Exclusively By

PERSONAL SOFTWARE INC.

Program ©1981 By Micro Finance Systems
Pocket Reference ©1981 By Personal Software Inc.

PART NUMBER: 10939-33100

4/81

MOVING THE CURSOR

Moves the cursor left and right within the menus and up and down within

the lists.

SPACE Bar Switches lines within the menus.

KEY USAGE

CTRL-C Cancels a function, such as printing or drawing a chart, that is already in

operation.

ESC Erases the last character entered from the keyboard. In the EDIT

function, enters the Edit command menu. Erases the status area when a

chart is displayed.

I,J,K, and M Moves a moveable title in the direc-

tion indicated by the relative position of the key-up (I), down (M), right

(K), and left (J).

REPT Automatically repeats any other key

that is depressed.

RESET SHOULD NOT BE USED. When

accidentally pressed, usually returns to the highest level menu in the

current program.

RETURN Selects the menu or list item to which

the cursor currently points and enters alphanumeric data typed at

the keyboard.

SPACE Bar Marks a list item with an asterisk (*) for selection when multiple selection

is allowed. Also deselects a selected item. Functions the same as the RETURN key when multiple selec-

tion is not allowed.

Y Affirmative response to prompts requesting confirmation, such as

changing programs and deleting files. Any key except Y cancels the

operation.


Controls the speed of a moveable 0-9

title-stop (0) to slow (1) to fast (9).


DATA ENTRY

Data is entered from the keyboard when the message in the status area requests it. Numeric data must be entered in decimal format. The program converts large numbers (greater than 9 digits) and small numbers (less than, .001) to exponential format, for example, if you enter 3400000000 the program displays 3.4E+10.


THE VISIPLOT CHART




VISITREND PROGRAM STATUS AREA



STORAGE MANAGEMENT PROGRAM STATUS AREA



PLOT PROGRAM STATUS AREA



SOME VISITREND/VISIPLOT DEFINITIONS

DATA POINT A numeric value associated with a

date; the value plotted against the

X-axis.

LIST

FILE A collection of 1 to 16 data series on

a diskette.

A display offering a collection of data items, one or more of which can

be selected.

PERIOD The frequency of data points within

a year.

RANGE

The period of time covered by a

series. It is plotted on the X-axis.

SCALE

The scope of values covered by the

Y-axis of a chart.

FILE NAME OUALIFIERS

The VisiTrend/VisiPlot program generates data series based on source series specified during function invocation. The generated series use the name of the source with one of the following qualifiers added.

FUNCTION QUALIFIER

MOVE AVG . Mn n = number of periods averaged.

SMOOTH .S %CHANGE .%

LAG .-n n = number of periods lagged.

LEAD .+n n = number of periods leading.

TOTAL .T

REGRESS .Fn Fitted series; n is program supplied.

.Rn Residual series; n is program

supplied

MENU FUNCTIONS

STORAGE MANAGEMENT PROGRAM

Main Storage Management Menu



LOAD

Load file of series from diskette to

memory.

->PLOT


Go to the Plot program.

LOOKUP

List data series currently in memory.

CLEAR Delete data series from memory. <MORE> Go to the main menu extension. Invoke the data entry and editing EDIT function. ->TREND Go to the VisiTrend program. SAVE Write data series to file on diskette. NORMAL Save data in Visiplot data format. DIF Save data in DIF format. OUIT Transfer control to Applesoft Basic. DRIVE Change data diskette drive number. INIT Initialize a diskette for VisiPlot use. DELETE Delete files from the data diskette permanently. SLOT Change the data diskette slot number. MAIN Return to the main menu.

Edit Command Menu



To change an entry, move cursor to entry, type new value, and press RETURN or right arrow key.

To add a value to the end of a series, move the cursor beyond the end, type new value, and press RETURN or right arrow key.

The commands take place at the cursor location in the series.

JUMP

Move cursor to end of, beginning of, or date within a series.

INSERT Add 1 or more data points to the series.

DELETE Delete data points from the series.

SPECS Change the data series specifications.

NAME Change the series name.

PER Change the series period.

START Change the series start date.

EXIT Return without making change.

FORMAT Change the data format (fixed format with degree of precision or floating point) and column width.

PRINT Print the contents of the screen

PRINT Print the contents of the screen.

UNDO Remove all changes made in this edit session.

EDIT Return to the Edit entry level.

FILL Add data to the series.

EXIT

ARITH Add data in arithmetic progression.

GEOMET Add data in geometric progression.

INSERT Add a whole series from memory.


INTERP Interpolate for zero

INTERP Interpolate for zero values between points.

EXIT Return without adding data.

Return to the Main Storage Management menu and save series.

VISITREND PROGRAM Main Menu



EDIT	Invoke the data entry and editing function.		
ANALYZE	Invoke statistical analysis functions.		
->MAIN	Return to the Main Storage Management program.		
LOOKUP	List data series currently in memory.		
FUNCTION	Invoke the series permutation functions.		
XFORM	Invoke the series transformation		

XFORM Capabilities

CLEAR

The XFORM function offers the following operators and functions:

Delete data series from memory.

Arithmetic Operators

+	Addition
_	Subtraction
*	Multiplication
/	Division
•	Exponention

Logical Operators

AND OR NOT

Comparative Operators

<	Less than	
<=	Less than or equal	
==	Equal	
>	Greater than	
>=	Greater than or equal	

Functions

(Variable (v) must be a series name—see Applesoft functions for further information.)

SGN(v)	Sign
INT(v).	Integer part of
SQR(v)	Square root
LOG(v)	Natural logarithm
EXP(v)	e to the power of
RND(v)	Random number between 0 and 1
ABS(v)	Absolute value of
SIN(v)	Sine
COS(v)	Cosine
TĀN(v)	Tangent
ATN(v)	Arctangent

Parentheses () can be used anywhere to change the natural order of execution and improve readability.

Analyze Menu




TABLE List one or more series by date.

STATS Generate descriptive statistics for one or more series.

UNLABEL

Remove axis labels (takes immediate

effect).

BOTH

Remove X- and Y-axis

labels.

HORIZ VERT Remove X-axis labels.

RT

Remove Y-axis labels.

NONE

Return to main menu.

RESCALE

Change the program set Y-axis scale

(effective next PLOT).

BACKGR

Change the background color - also changes the plotting color; displays color menu (effective next PLOT or


OVERLAY).

COLOR

Change the plotting color; displays color menu (effective next PLOT or

OVERLAY).

Title Menu



EXIT

Return to Main Plot menu.

TOP

Put title at top of chart (normal or

bold typeface).

BOTTOM1

Put title at bottom of chart (normal or

bold typeface).

BOTTOM2

Same as BOTTOM1 but second line.

воттом3

Same as BOTTOM1 but third line.

LEFT

Put vertical title along Y-axis (normal

typeface only).

LEGEND

Return the legend lines covered by bottom titles (removes legend from


pie chart).

MOVEABLE

Put title anywhere on chart—use I, J, K, and M keys to move title, 0 through 9 to control speed (normal typeface

Color Menu


only).



Color	Code	Black and White Representation
DEFAULT		Black background, white plotting
BLACKI	Bl	Black
GREEN	GR	Grey
VIOLET	VI	Grey
WHITEI	Wl	White
BLACK2	B2	Black
ORANGE	OR	Grey
BLUE	BL	Grey
WHITE2	W2	White

COLOR CODE
W1.B1
Plotting Background
Color Color

Main Plot Menu



P	L	0	T

Draw the chart type with the current

series.

SELECT

Go to the Select menu.

WINDOW

Display the window menu.

EXIT

Return to the Main Plot

menu.

HORIZ

Create top and bottom

windows.

VERT

Create left and right

windows.

SWITCH

Switch to the other win-

dow.

NONE

Return to single window mode.

mode

PRINT

Print the currently displayed chart

on the graphic printer.

PIXSAVE

Save the currently displayed chart in

binary form on diskette for later

printing by another program.

OPTIONS

Go to the Options menu.

->MAIN

Go to the Storage Management

program.

OVERLAY

Draw the current series over the


currently displayed chart.

NEW

Erase current chart, reset all options

to the defaults.

Options Menu



TITLE

Go to the Title menu (takes immedi-

ate effect).

RANGE

Change the current range (effective-

next PLOT).

SET

Specify a new range.

CLEAR F

Return to program

established range.

EXIT

Return without chang-

ing range.

FORMAT

Change the current chart display

format (effective PLOT or OVER-

LAY).

Line chart-SYMBOLS, LINES, or

BOTH.

Bar chart-OUTLINE, SHADED, or

SOLID.

Scatter chart - SYMBOLS or

POINTS.

GRID

Draw grid lines; removes existing grid lines (takes immediate effect).

BOTH

Draw or remove hori-

zontal and vertical grid

lines.

HORIZ

Draw or remove hori-

zontal grid lines.

VERT

Draw or remove vertical

grid lines.

NONE

Return to Main menu.

REGRESS

Do linear multiple regression and trendline forecasting; generates fitted

and residual series.

FORMAT


Change the data format (fixed format with degree of precision or float-

ing point) and column width.

EXIT

Return to the Main VisiTrend menu.

Function Menu



MOVE AVG

Generate a series containing the moving average of the source series.

SMOOTH

Generate a series containing a single exponentially smoothed version of the source series.

%CHANGE

Generate a series containing the percent of change between points in the source series.

LAG

Generate a series containing a lagging version of the source series.

LEAD

Generate a series containing a leading version of the source series.

TOTAL


Generate a series containing the cumulative total of the points in the

source series.

EXIT

Return to the Main VisiTrend menu.

PLOT PROGRAM Select Menu



LINE

Draw line chart (select one or more series).

BAR

Draw vertical bar chart (select one or more series; multiple series are stacked).

NORMAL Full-width bors centered

on tick marks.

LEFT

Half-width bars to left of

tick marks.

RIGHT

Half-width bars to right of tick marks to draw comparison charts (left and right bars). PLOT first bar and OVERLAY second—change FOR-MAT or COLOR so bars can be distinguished.

AREA

Draw area chart (select one or more series).

PIE

Draw pie chart of values from same date in different data series (select

two or more series).

HI-LO

Draw vertical lines between high and low points at each date (separate prompts for two series).

SCATTER

Draw a scatter chart (separate prompts for two series).

NONE

Go to Main Plot menu.